```
How to Install MySQL Server 8.0 on Windows 10
 2
 3
    1. Visit and Downloads
 4
       1) Visit <a href="https://downloads.mysql.com/archives/installer/">https://downloads.mysql.com/archives/installer/</a>
 5
       2)Downloads
         -Product Version: 8.0.28.0
 6
 7
         -Operating System: Microsoft Windows
 8
          -Windows (x86, 32-bit), MSI Installer: 435.7M
 9
            --mysql-installer-community-8.0.28.0.msi
10
11
12
    2. MySQL 8.0 Installation
13
       1)Choose a Setup Type
14
         -Custom
          -Next
15
16
17
       2)Select Products
         -MySQL Servers
18
19
            --MySQL Server\MySQL Server 8.0\MySQL Server 8.0.28 - X64
20
         -Applications
            --MySQL Workbench\MySQL Workbench 8.0\MySQL Workbench 8.0.28 - X64
21
22
         -MySQL Connectors
23
            --Connector/J \ Connector/J 8.0\Connector/J 8.0.28 - X86
24
         -Documenetation
25
            --MySQL Documentation\MySQL Documentation 8.0\MySQL Documentation 8.0.28 - X86
         -Samples and Examples
26
27
            --Samples and Examples 8.0\Samples and Examples 8.0.28 - X86
28
         -Next
29
       3)Check Requirments
30
31
          -Execute
32
          -Microsoft Visual C++ 2015 Redistributable (x64) - 12.0.40660 Install
33
         -Microsoft Visual C++ 2015-2019 Redistributable (x64) - 14.28.29914 Install
34
         -Next
35
36
       4)Installation
37
         -Execute > Next
38
39
       5)Product Configuration
40
          -Next
41
         [MySQL Server 8.0.28]
42
            --Type and Networking
43
               ---Config Type : Develoment Computer
44
               ---Connectivity
45
                  ----TCP/IP
46
                  ----Port: 3306
47
                  ----Open Windows Firewall port for network access : check
48
               ---Next
49
            --Authentication Method
50
               ---Use Strong Password Encryption for Authentication (RECOMMENDED): check
51
52
            -- Accounts and Roles
53
               ---MySQL Root Password: mymysql
54
               ---Next
55
            --Windows Service
56
               ---Configure MySQL Server as a Windows Service : check
               ---Windows Service Name: MYSQL80
57
58
                  ----Start the MySQL Server at System Startup : check
59
               ---Run Windows Service as ... : Standard System Account
60
               ---Next
            --Apply Configuration
61
               ---Execute
62
63
            --Finish
64
         -Next
         [Sample and Examples]
65
            -- Connect To Server
66
               ---User name: root
67
```

```
68
               ---Password: mymysql
 69
               ---Check Click
 70
                ---Next
 71
             --Apply Configuration
 72
                ---Execute
 73
             --Finish
 74
          -Next
 75
 76
        6)Installation Complete
 77
          -Start MySQL Workbench after setup: Uncheck
 78
          -Finish
 79
 80
 81
     3. Post-installation Check
 82
        1)Windows Service
 83
          -services.msc
 84
             -- MYSQL80: Running
 85
        2)Windows Explorer
 86
          -C:/Program Files/MySQL/MySQL Server 8.0
 87
 88
          -C:/Program Files/MySQL/MySQL Workbench 8.0
 89
          -C:/Program Files (x86)/MySQL/Connector J 8.0
 90
          -C:/Program Files (x86)/MySQL/MySQL Documentation 8.0
 91
          -C:/Program Files (x86)/MySQL/MySQL Installer for Windows
          -C:/Program Files (x86)/MySQL/Samples and Examples 8.0
 92
 93
          -C:/ProgramData/MySQL/MySQL Installer for Windows: Hidden
 94
          -C:/ProgramData/MySQL/MySQL Server 8.0 : Hidden
 95
 96
 97
     4. Login MySQL
 98
        1)In Command Window,
 99
          > cd C:/Program Files/MySQL/MySQL Server 8.0/bin
100
          > mvsal
          ERROR 1045 (28000): Access denied for user 'ODBC'@'localhost' (using password: NO)
101
102
103
          > mysql -h localhost -u root -p
          Enter password: mymysql
104
105
106
          Welcome to the MySQL monitor. Commands end with; or \g.
107
          Your MvSOL connection id is 19
          Server version: 8.0.29-log MySQL Community Server (GPL)
108
109
110
          Copyright (c) 2000, 2021, Oracle and/or its affiliates.
111
112
          Oracle is a registered trademark of Oracle Corporation and/or its
113
          affiliates. Other names may be trademarks of their respective
114
          owners.
115
116
          Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.
117
118
          mysql>SELECT VERSION();
119
          mysql>SELECT USER(), NOW();
120
          mysql>exit
121
          Bye
122
123
        2) Windows Path Registration
124
          -SystemPropertiesAdvanced
          -환경변수
125
126
          -시스템 변수
127
             --Path > 편집
128
                --새로 만들기 > C:/Program Files/MySQL/MySQL Server 8.0/bin
129
130
          -In Command Window,
131
             >set PATH
132
             >echo %PATH%
133
134
```

135	5. Create Database and Create User
136	1)Create User
137	mysql>CREATE USER 'scott'@'%' IDENTIFIED BY 'tiger';
138	Query OK, 0 rows affected (0.01 sec)
139	
140	mysql> GRANT ALL PRIVILEGES ON *.* TO 'scott'@'%';
141	Query OK, 0 rows affected (0.00 sec)
142	
143	mysql> FLUSH PRIVILEGES;
144	Query OK, 0 rows affected (0.00 sec)
145	
146	2)Create Database
147	mysql>CREATE DATABASE mycompany;
148	Query OK, 0 rows affected (0.00 sec)
149	
150	3)Sample Data Registration
151	mysql>use mycompany;
152	mysql>source C:/Temp/scott.sql